


DA62 Oxygen Pressure Gauge with Raspberry Pi Pico and 1.28-inch LCD Screen (Implemented as a Mobiflight Community Board)



Hardware:

- Raspberry Pi Pico
 - <https://tinyurl.com/2h8rs7u3>
 - <https://tinyurl.com/4s2kzhkw>
- 1.28 in round LCD (GC9A01)
 - <https://tinyurl.com/cvtb823y>
 - <https://tinyurl.com/3nby3jny>
 - Note: If you want to use the simple case I designed, get the one with the specific form factor below.



- USB connectors, wires, etc.
- Raspberry Pi Pico and LCD Screen PIN connections. Connect your Raspberry Pi Pico and the LCD screen according to the pins below:

LCD Screen PIN	Raspberry Pi Pico PIN
GND	GND
VCC	3V3
SCL	18
SDA	19
RES	21
DC	20
CS	17
BLK	16


Software:

- Mobiflight
 - <https://www.mobiflight.com/en/index.html>
 - Official documentation on how to add Mobiflight Community Boards:
 - <https://github.com/Mobiflight/MobiFlight-Connector/wiki/User-guide-%E2%80%90-Community-Board-and-Custom-Devices>

Instructions

1. Download the DA62 Project Oxygen Gauge Mobiflight Community Template Project as a Zip file from Github.
 - <https://github.com/savesabanal01/CommunityTemplate>
2. Unzip the project in your local folder. The DA62 Oxygen Gauge Mobiflight Community is in the folder “dist.” It is a file called “DA62_Oxygen_Gauge_2.5.1.zip”
3. Install the DA62 Oxygen Gauge Mobiflight Community Board.
 - The official documentation to install a Mobiflight Community Board can be found here: <https://github.com/Mobiflight/MobiFlight-Connector/wiki/User-guide-%E2%80%90-Community-Board-and-Custom-Devices>
 - Detailed Steps:
 - i. Open you Windows Explorer, using Win+E
 - ii. In the file path window, paste %LocalAppData%\MobiFlight\MobiFlight Connector\Community
 - iii. Unzip the “DA62_Oxygen_Gauge_2.5.1.zip”
 - iv. Restart MobiFlight Connector
4. Upload the DA62 Oxygen Gauge Mobiflight Community Board
 - Start the Mobiflight Connector

- Connect the Raspberry Pi Pico to your computer
- Ignore any firmware update notification by MobiFlight
- Select the “Raspberry Pi Pico” from the list of boards




- **Optional step:** In case the board currently has official MobiFlight firmware installed, "Reset Board" first.
- Right-click on the board again, now you will have additional options available. Choose to update the firmware with “Community” -> “DA62 Oxygen Gauge RaspiPico”
- Confirm the update firmware dialog


5. Adding Custom Devices

- Right click on the “DA62 Oxygen Gauge” Community Board
- Choose “Add device” -> “Custom Devices” -> 3S Simulations DA62 Oxygen Gauge”

- Click “Upload config”. It will give an error, but you can ignore it.



- Click “Ok” in the “Settings” menu to close it. It will give a warning but you can ignore this also.



6. Using the DA62 Oxygen Gauge Custom Device

- Create a new Output Config. Please see the examples below:

DA62.mcc - MobiFlight Connector (10.2.2)


File Extras Help

Save Run Test Stop AutoRun MobiFlight Modules Donate Discord HubHop YouTube Exit


Output configs Input configs

Active	Description	Module	Output	Type	Flight Sim Value	Output Value	Edit
<input checked="" type="checkbox"/>	Audio Panel PA LED	Audio Panel	LED9	LED / Output			...
<input checked="" type="checkbox"/>	Audio Panel SPKR LED	Audio Panel	LED10	LED / Output			...
<input checked="" type="checkbox"/>	Audio Panel MKRMUTE LED	Audio Panel	LED11	LED / Output			...
<input checked="" type="checkbox"/>	Audio Panel HI SENS LED	Audio Panel	LED12	LED / Output			...
<input checked="" type="checkbox"/>	Audio Panel DME LED	Audio Panel	LED13	LED / Output			...
<input checked="" type="checkbox"/>	Audio Panel NAV1 LED	Audio Panel	LED14	LED / Output			...
<input checked="" type="checkbox"/>	Audio Panel ADF LED	Audio Panel	LED15	LED / Output			...
<input checked="" type="checkbox"/>	Audio Panel NAV2 LED	Audio Panel	LED16	LED / Output			...
<input checked="" type="checkbox"/>	Audio Panel AUX LED	Audio Panel	LED17	LED / Output			...
<input checked="" type="checkbox"/>	Audio Panel MAN SQ LED	Audio Panel	LED18	LED / Output			...
<input checked="" type="checkbox"/>	Audio PanelPLAY LED	Audio Panel	LED19	LED / Output			...
<input checked="" type="checkbox"/>	Audio Panel PILOT LED	Audio Panel	LED20	LED / Output			...
<input checked="" type="checkbox"/>	Audio Panel COPILOT LED	Audio Panel	LED21	LED / Output			...
<input checked="" type="checkbox"/>	Oxygen Pressure	-	-				...
<input checked="" type="checkbox"/>	Instrument Brightness	MobiFlight RaspiPico	3S Simulations DA62 Oxygen Gauge				...
<input type="checkbox"/>	Double-click row to add new config...						...

- Click on the Edit-Button (...) to open the Output Config Wizard
- In the Output Config Wizard, click on Display tab
- Select “DA62 Oxygen Gauge...” from the list of “Module”
- Select “CustomDevice” from “Use Type of”
- Under the “Display Settings”, choose “3S Simulations DA62 Oxygen Gauge”
- Under “Message Type”, choose the following:
 - For the Oxygen Gauge PSI value, choose “Oxygen Gauge PSI Value”
 - **Important Note:** The Oxygen PSI Value needs to be the actual value. Please do a transformation if your simulator does not return the actual value.
 - For the brightness settings, choose “Instrument Brightness”
 - **Important Note:** The “Instrument Brightness” value needs to be ration between 0 and 1. Please do a transformation if your simulator does not return the brightness ratio between 0 and 1.



- For X-Plane (tested with X-Plane 11) the following Datarefs can be used:
 - For Oxygen PSI Value:
sim/cockpit2/oxygen/indicators/o2_bottle_pressure_psi
 - For Instrument Brightness:
sim/cockpit2/electrical/instrument_brightness_ratio_manual[1]




- This is not tested with MSFS2020 since I don't have it, but you can try with MSFS2020 variables such as "Oxygen Pressure PSI" and "LIGHT BACKLIGHT INTENSITY"

Optional:

If you want to print the simple casing I designed, the STLs for 3D printing it are located in the "Casing Design" folder.

Casing Assembly:



And most important of all:

- **Have fun!!**
- **Mobiflight Rocks!!**